
Subject: Moving the Geometry from data file to the parameters
Posted by [Mohammad Al-Turany](#) on Tue, 22 Sep 2009 22:08:47 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hello,

As was discussed a few months ago, the geometry is moved from the data files to the parameter file, this make the fRun->LoadGeomerty() method obsolete, and requires loading the parameters wherever the geometry is needed. usually this is the case for digi and reco macro, and I modify the event display macro to do the same.

please test it and let me know.

Mohammad

Subject: Re: Moving the Geometry from data file to the parameters
Posted by [Tobias Stockmanns](#) on Wed, 23 Sep 2009 07:33:36 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi Mohammad,

thank you for this important step.

Do you have some example macros where one can see the use of the parameter file with the geometry data?

Cheers,

Tobias

Subject: Re: Moving the Geometry from data file to the parameters
Posted by [Mohammad Al-Turany](#) on Wed, 23 Sep 2009 08:21:52 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

Yes, for the sim macros nothing changed, all reco macros which use the parameters are also not effected, the geometry is build automatically. I had only to add the parameter file handling to the event display macro (macro/run/eventdisplay.C).

Anyway for Geane and some code there will be some small changes, and this work is ongoing.

Mohammad

Subject: Re: Moving the Geometry from data file to the parameters
Posted by [Mohammad Al-Turany](#) on Wed, 23 Sep 2009 14:55:47 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hi,

For those who wants to see or use the geometry from plain root I found an easy way to do it, namely:

```
Quote:gROOT->LoadMacro("$VMCWORKDIR/gconfig/rootlogon.C");
rootlogon();
```

```
TFile* file = new TFile("testparams.root");
file->Get("FairBaseParSet");
```

```
// now the geometry is available as TGeo in memory
```

```
gGeoManager->GetMasterVolume()->Draw("ogl");
```

regards

Mohammad

Subject: Re: Moving the Geometry from data file to the parameters
Posted by [Dima Melnychuk](#) on Wed, 07 Oct 2009 16:47:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi Mohammad,

I tried to access geometry from the parameter file in the following way:

```
gROOT->LoadMacro("$VMCWORKDIR/gconfig/rootlogon.C");
gROOT->LoadMacro("$VMCWORKDIR/gconfig/basiclibs.C");
rootlogon();
basiclibs();
```

```
FairRunAna *fRun= new FairRunAna();
fRun->SetInputFile("sim_emc.root");
fRun->SetOutputFile("test.root");
fRun->Init();
```

```
TString parFile = "simpars.params.root";
FairRuntimeDb* rtDb = fRun->GetRuntimeDb();
FairParRootFileIo* parInput1 = new FairParRootFileIo();
parInput1->open(parFile.Data());
rtDb->setFirstInput(parInput1);
```

```
FairBaseParSet* par=(FairBaseParSet*) (rtDb->getContainer("FairBaseParSet"));
geom = par->GetGeometry();
```

sim_emc.root and simparams.root are files produced by /macro/emc/sim_emc.C

I supposed that "geom" should be a pointer to TGeoManager. But it is 0 in this case. What is wrong here?

I tried to create emc initialization task to initialize properly EmcMapper and I need access to TGeoManager there.

Dima

Subject: Re: Moving the Geometry from data file to the parameters

Posted by [StefanoSpataro](#) on Wed, 07 Oct 2009 16:51:57 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi Dima,

I think that after your:

FairBaseParSet* par=(FairBaseParSet*) (rtdb->getContainer("FairBaseParSet"));

you access to the geometry with gGeoManager, without geom = par->GetGeometry();

Try to use gGeoManager and let me know. This global object should be created automatically just after the parameter call, and then you can use it without creating it.

Subject: Re: Moving the Geometry from data file to the parameters

Posted by [Mohammad Al-Turany](#) on Wed, 07 Oct 2009 17:30:02 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hallo Dima and Stefano,

Dima, in the macro you show here you should set the Runtime data base before the init of the run, and the last two lines are not needed because this is done internally, so your macro will look like:

Quote:

```
gROOT->LoadMacro("$VMCWORKDIR/gconfig/rootlogon.C");
gROOT->LoadMacro("$VMCWORKDIR/gconfig/basiclibs.C");
rootlogon();
basiclibs();
```

```
FairRunAna *fRun= new FairRunAna();
fRun->SetInputFile("sim_emc.root");
fRun->SetOutputFile("test.root");
```

```
TString parFile = "simparams.root";
FairRuntimeDb* rtdb = fRun->GetRuntimeDb();
FairParRootFileIo* parInput1 = new FairParRootFileIo();
```

```
parInput1->open(parFile.Data());
rtdb->setFirstInput(parInput1);

fRun->Init();

geom = gGeoManager;
```

In fact the geometry is now a parameter like any other parameter, except that it is a parameter of a RUN, just like the field or beam momentum, and because ROOT has the global variable gGeoManager which is set internally, there is no need to you or anybody to try to get himself from the parameter file. So in any Task which is added to the run you can simply use the gGeoManager in the init of your task or anywhere except in the ctor or the method SetParTask() because at the time when they are called the Parameter containers are still not initialized.

regards

Mohammad

Subject: Re: Moving the Geometry from data file to the parameters
Posted by [Mohammad Al-Turany](#) on Wed, 07 Oct 2009 17:36:57 GMT
[View Forum Message](#) <> [Reply to Message](#)

Hallo again,

Stefano: the line of code you wrote before:

Quote:

FairBaseParSet* par=(FairBaseParSet*) (rtdb->getContainer("FairBaseParSet"));

is called in the FairRunAna, so there is no need to call it yourself! Moreover after connecting a parameter file and calling the FairRunAna::Init(), the gGeoManager should be a valid pointer (if there was a geometry used in the parameters!). and can be used.

Mohammad.
