

---

Subject: Problem on running FairRoot tutorial macro  
Posted by [kamalpdutta](#) on Sat, 13 Dec 2014 09:12:02 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Dear All,

I have just builded FairRoot on my ubuntu 14.04 32 bit machine with <https://github.com/FairRootGroup/FairSoft>. But I am getting problem on running tutorials. For example on running Tutorial1, following error is shown

```
Processing run_tutorial1.C...
Error: Symbol FairRunSim is not defined in current scope run_tutorial1.C:61:
Error: Symbol FairRunSim is not defined in current scope run_tutorial1.C:61:
Error: type FairRunSim not defined
FILE:/home/kamalpdutta/PANDA/buildFairRoot/share/fairbase/example/Tutorial1/./run_tutorial1.C LINE:61
Error: Invalid type 'FairRunSim*' in declaration of 'run' run_tutorial1.C:61:
*** Interpreter error recovered ***
```

Please help me regarding this.

regards  
Kamal Dutta

---

---

Subject: Re: Problem on running FairRoot tutorial macro  
Posted by [Florian Uhlig](#) on Sat, 13 Dec 2014 09:29:31 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

did you setup the environment correctly? This is done by running the following command to execute a script in your build directory.

```
source <build_dir>/config.sh
```

<build\_dir> has to be changed to your build directory.

Ciao

Florian

---

---

Subject: Re: Problem on running FairRoot tutorial macro  
Posted by [kamalpdutta](#) on Sat, 13 Dec 2014 09:54:08 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi Ciao,

Thanks for your qick reply. Yes I did source config.sh in my build directory. It echo following

System during compilation: Ubuntu 14.04.1 LTS  
i686  
System now : Ubuntu 14.04.1 LTS  
i686

But still showing the same error.

regards'  
Kamal Dutta

---

Subject: Re: Problem on running FairRoot tutorial macro  
Posted by [kamalpdutta](#) on Wed, 17 Dec 2014 06:12:46 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi Ciao and all,

Installing external dec-14 version and new FairRoot v-14.11, I am able to run FairRoot Tutorials. But its shows the following bug,

```
Loading Geant3 libraries ...  
dlopen error: /home/kamalpdutta/PANDA/EXTERNAL/dec14/lib/libgeant321.so: undefined  
symbol: pycomp_  
Load Error: Failed to load Dynamic link library  
/home/kamalpdutta/PANDA/EXTERNAL/dec14/lib/libgeant321.so  
Warning: Return value of void g3libs() ignored  
/home/kamalpdutta/PANDA/FairRoot-v-14.11/example/gconfig/g3libs.C:26:  
Error: Symbol TGeant3 is not defined in current scope  
/home/kamalpdutta/PANDA/FairRoot-v-14.11/example/gconfig/g3Config.C:16:  
Error: Invalid type 'TGeant3*' in declaration of 'geant3'  
/home/kamalpdutta/PANDA/FairRoot-v-14.11/example/gconfig/g3Config.C:16:  
(long)0  
*** Interpreter error recovered ***  
SetCuts Macro: Setting Processes..  
Error: illegal pointer to class object gMC 0x0 2139  
/home/kamalpdutta/PANDA/FairRoot-v-14.11/example/gconfig/SetCuts.C:30:  
*** Interpreter error recovered ***  
  
*** Break *** segmentation violation
```

Can you please identify the source of this bug ?

regards

Kamal Dutta

---

Subject: Re: Problem on running FairRoot tutorial macro  
Posted by [Florian Uhlig](#) on Wed, 17 Dec 2014 08:37:56 GMT  
[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

Quote:Can you please identify the source of this bug ?

Can you please identify the macro which doesn't work. Can you please give some more information about your system (OS, compiler, ...).  
without this information it is hard to guess what could be the problem.

Ciao

Florian

---

Subject: Re: Problem on running FairRoot tutorial macro  
Posted by [kamalpdutta](#) on Wed, 17 Dec 2014 08:44:02 GMT  
[View Forum Message](#) <> [Reply to Message](#)

Dear Ciao,  
The error I have shown is for Tutorial1. I am using Ubuntu 14.04.1 32 machine. The external package installation log file is attached here, where you can get other details of my system.

regards  
Kamal Dutta

#### File Attachments

1) [Install\\_151214\\_141303.log](#), downloaded 271 times

---

Subject: Re: Problem on running FairRoot tutorial macro  
Posted by [Tonya Evdokimova](#) on Mon, 02 Feb 2015 08:38:29 GMT  
[View Forum Message](#) <> [Reply to Message](#)

Hello.

I can confirm this behaviour on 32 bit Ubuntu 12.04.05 LTS. GCC version 4.6.3 (Ubuntu/Linaro 4.6.3-1ubuntu5)

I installed new external packages fairroot jul14p3 + pandaroot (trunk) following the procedure from <https://panda-wiki.gsi.de/foswiki/bin/view/Computing/PandaRootInstallGit>.

Installation itself went without any problems. But if i try to run any sim macro:  
/run/sim\_complete.C or /emc/sim\_emc.C I've got exactly the same problem Kamal Dutta mentioned.

CINT/ROOT C/C++ Interpreter version 5.18.00, July 2, 2010

Type ? for help. Commands must be C++ statements.

Enclose multiple statements between { }.

root [0]

Processing sim\_emc.C...

[INFO ] FairRootManager::OpenOutFile("sim\_emc.root")

[INFO ] Media file used :

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/geometry/media\_pnd.geo

Error in <TClonesArray::SetClass>: called with a null pointer

-l container name PndEmcGeoPar

[INFO ] ===== FairRunSim: Initialising simulation run =====

Info in <TGeoManager::TGeoManager>: Geometry FAIRGeom, FAIR geometry created

[INFO ] FairGeoMedia: Read media

-l container name PndEmcDigiPar

-l container name PndEmcDigiNonuniformityPar

\*\*\*\*\*

initialisation for run id 1422865622

\*\*\*\*\*

-l- FairRunTimeDB::InitContainer() PndEmcGeoPar

[ERROR ] init() PndEmcGeoPar not initialized

-l- FairRunTimeDB::InitContainer() PndEmcDigiPar

PndEmcDigiPar initialized from Ascii file

-l- FairRunTimeDB::InitContainer() PndEmcDigiNonuniformityPar

[ERROR ] init() PndEmcDigiNonuniformityPar not initialized

Error in <FairRuntimeDb::initContainers(>: Error occured during initialization

[INFO ] PndFieldMap: Reading field map from ROOT file

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/input/TransMap.1500.root

[INFO ] PndFieldMap: Reading field map from ROOT file

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/input/DipoleMap1.1500.root

[INFO ] PndFieldMap: Reading field map from ROOT file

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/input/DipoleMap2.1500.root

[INFO ] PndFieldMap: Reading field map from ROOT file

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/input/SolenoidMap1.root

[INFO ] PndFieldMap: Reading field map from ROOT file

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/input/SolenoidMap2.root

[INFO ] PndFieldMap: Reading field map from ROOT file

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/input/SolenoidMap3.root

[INFO ] PndFieldMap: Reading field map from ROOT file

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/input/SolenoidMap4.root

[INFO ] ----- Standard Config is called -----

Loading Geant3 libraries ...

dlopen error: /home/uzbton/fairroot\_jul14/install/lib/libgeant321.so: undefined symbol: pycomp\_

Load Error: Failed to load Dynamic link library

/home/uzbton/fairroot\_jul14/install/lib/libgeant321.so

Warning: Return value of void g3libs() ignored

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/gconfig/g3libs.C:19:

Error: Symbol TGeant3 is not defined in current scope

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/gconfig/g3Config.C:9:

Error: Invalid type 'TGeant3\*' in declaration of 'geant3'

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/gconfig/g3Config.C:9:

(long)0

\*\*\* Interpreter error recovered \*\*\*

SetCuts Macro: Setting Processes..

Error: illegal pointer to class object gMC 0x0 4010

/home/uzbton/fairroot\_jul14/fairsoft\_jul14p3/pandaroot/gconfig/SetCuts.C:23:

\*\*\* Interpreter error recovered \*\*\*

I have installed previous version of Fairroot (dec13) and pandaroots (23950 trunk and jan14 release) it works without problems.

Please give me a hint how to solve this issue.

Thank you.